Product information No. 465A February 2018



Release of OJ-Air2 software version 4.22

OJ-Air2 software version 4.22 is released for up-grade with the SD-card. In the production at OJ Electronics the version 4.13 is still used, until further notice.

Changes

Compared to version 4.21 there were following improvements:

Functionality

Rotary heat exchanger is now active in CO₂ modulated recirculation mode (Bug introduced in 4.18)

Web.

No changes

OJ-Air2-HMI-35T

No changes

Hand terminal

No changes

Alarms

No changes

Modbus registers

- Added: 1x0320 Cool_RE2 Cooling Relay 2
- Added: 1x0321 Cool_RE3 Cooling Relay 3
- Added: 1x0322 Cool_RE4 Cooling Relay 4

See protocol on OJ Electronics' website.



BACnet

- Added: bi 277 Alr_FireEvaDmp Alarm smoke evacuation damper is activated
- Added: bi 278 Heat_RE2 Heating relay 2
- Added: bi 279 CombiTSenErr Combi coil Return sensor
 Sensor fault
- Added: bi 280 CombiFrostAlrH Combi coil Frost alarm
- Added: bi 282 CombiFrostReg Combi coil Frost protection active
- Added: bi 282 CombiPumpExer Combi coil

pump exercising active

- Added: bi 283 CombiCoolRel Combi coil, Cooling relay
- Added: bi 284 CombiHeatRel Combi coil, Heating relay
- Added: ai 126 CombiBattTemp Combi coil return temp.
- Added: av 275 CombiUpStPow Combi coil Start-up output setpoint
- Added: av 287 CombiPumpFunc 0=Constant, 1=Valve open%, 2=Outdoor
- Added: av 288 CombiPmpStTmpH Start temp. for circulation pump Combi coil
- - Added: av 290 CombFrzStopSet Combi coil Setpoint for frost protection in stop
- Added: av 291 CombFrzDrSetH Combi coil Setpoint for frost protection in Operation mode
- Added: av 292 CombiFrzPB Combi coil P-band for Frost protection control
- Added: ac 293 CombiFrzAlHSet Combi coil Setpoint for frost protection temp. alarm

See protocol on OJ Electronics website.

Affected articles

OJ-Air2Master

Coming into force

Version 4.22 is released for up-grade with SD-Card in week 06 2018.

Compatibility

No changes are required when up-grading from version 4.21 to 4.22.

Updating with the SD card

The OJ-Air2Master has to be with software version 2.01 or higher. The following files must be copied to the SD card:

- "air2_v422 update jffs2.tar.gz"
- "version.crc" (1kB, 06-02-2018, 09:19)

The files are available at

:http://www.ojelectronics.com/Support/Customer-Login.aspx



